



How to Download, Install & License SpatialXL

Contents

How to Download, Install & License SpatialXL	1
Download	1
Before Installing.....	2
Install.....	2
License	7
Check and Update to the Latest Software Version	13
Troubleshooting	14

Download

1. Go to <https://primethought.biz/>
2. Click on “Product Downloads” in the navigation bar.

About Us ▾ Help ▾ Spatial BI ↗ Mine Services ↗ Newsroom **Product Downloads**

3. Under “Product”, click on “SpatialXL” to start downloading the latest version.

Product Downloads


Product	Version	Release Notes
SpatialXL ↗	11.2.0.4	11.2.0.4 Release Notes

Before Installing


- Close Excel before you begin installation.
- Occasionally certain anti-virus software can interfere with installation. If your software does not install correctly, we recommend switching off the anti-virus and running the installation again.

Install


1. Once the SpatialXL install file is downloaded, double click on it to run it.
2. Select 'Install for me only (recommended)'. If you want to install for all users, you will need admin rights.




3. Click 'Next'.




4. Read and accept the license agreement, then click 'Next':




5. Optionally change the start menu folder that the program's shortcuts will be stored in, otherwise accept the default and click 'Next':




6. If you want a desktop shortcut to be created for the program, check this on, then click 'Next':




7. Click 'Install':




8. Installation will commence:



9. Click 'Finish':



10. Open up Excel and open up any workbook. You should now see a SpatialXL tab there. If you do not please contact PrimeThought for assistance.




Congratulations, you have now installed SpatialXL on your computer!

License

1. Open up Excel and open up any workbook.

2. Click on ‘About SpatialXL’ in the SpatialXL tab.




3. Click the ‘Update License’ button:




4. This will bring up the ‘SpatialXL Licensing information’ dialogue. You have 3 different licensing options here.

- ‘Cloud License’. If you have a cloud license, enter in your license credentials here, then optionally choose to have your password saved so you do not have to enter it each time you log in to SpatialXL. Then click ‘OK’.




- ‘Local License File’. This is a local license file (with a .lic extension) that is sent to by PrimeThought. Click the ‘Load license from file’ button and browse to the license file.




Then click 'OK' when done.


- 'Server License'. This is a license stored on a server that uses our concurrent network licensing service. Enter the license server URL here then click 'OK'.



5. You are now licensed and your license details will display by the License Status field at the bottom:



You can exit out of this dialogue now and then click ‘Show SpatialXL’.




Check and Update to the Latest Software Version

You can update to the latest version right within SpatialXL itself. Simply go to “About SpatialXL” in the SpatialXL ribbon of Excel.



Then, in the About SpatialXL dialogue, click the File pull-down menu and select “Check for updates”.



It will then let you know whether a later version of SpatialXL is available, and you will be able to download it from here:



You can now also request a license or send your machine info using the “Request License” and “Send Info...” buttons found in the File pull-down menu as well.

Troubleshooting

When I install SpatialXL I do not see the SpatialXL tab appearing in Excel.

Sometimes the add-in is not activated in Excel. You can turn on this add-in by going to the File > Options > Add-ins > Manage Com add-ins > Go You can then activate the SpatialXL add-in by making sure it is selected and pressing OK.

Support



T: +27871354351

support@primethought.biz - primethought.biz

Kyalami Estate, Midrand, Johannesburg,
1684, South Africa

